



S-TI-S JJ Simulation.vi

C:\Users\yg\Box\Guang Yue uiuc research box folder\computation\Labview
simulation GUI\S-TI-S JJ Simulation.vi

Last modified on 4/22/2020 at 10:14 AM

Printed on 4/22/2020 at 10:35 AM

1. before run, set the paramaters on the left of the screen.
2. flux (magnetic field) is in unit of flux quanta.
3. Phaserange is in the unit of Pi, the CPR will be build up according to phase range of $[-\text{Phaserange}/2, \text{Phaserang}/2]$, and such CPR will be a periodic function with Phaserange as period. Enter integer number of multiple times of 4 is preferred.
4. Use the step setting tab to set resolution of the calculation, you can set how many points is used to define the width of the Josephson junction, how many points to represent the Phaserange
5. Then you can choose which type of the CPR is used.
6. Depending on the choose of the CPR, you may want to set the strength of the MBS, "a" parameter, the width of the gaussian function used, and the pattern of parity of MBS. Parity pattern has to have same number of elements for positive and negative range.
Enter the parity 1 or -1 for positive and negative phase $+\text{Pi}$, $+\text{3Pi}$, $+\text{5Pi}$ etc.. in to the two arrays.
7. You can use the index control to read the array elements, then enter the value, you can also delete an element of array by right click, the number of array elements is not limited.
8. You can change the x,y range, zoom, create cursor etc. to help analyse the plot.
Right click to save the data into excel.

Enjoy!

Guang Yue



flux start

Set the flux lower bound for calculation



flux end

Set flux upper bound for calculation



flux step

Set flux step resolution.



stop

Stop the calculation of diffraction pattern, phase0



Geometry steps

Number of data points describe the y dimension of the JJ



S-TI-S JJ Simulation.vi

C:\Users\yg\Box\Guang Yue uiuc research box folder\computation\Labview
simulation GUI\S-TI-S JJ Simulation.vi

Last modified on 4/22/2020 at 10:14 AM

Printed on 4/22/2020 at 10:35 AM



CPR Type

Choose type of CPR: regular Josephson effect, non-local MBS, local MBS with same parity, local MBS with different parity for each MBS.



Tab Control



Phase steps

Data points describe the Phase space, $[-\text{PhaseRange}/2, \text{PhaseRange}/2]$.



Gaussian width

Gaussian function width to localize the MBS.



parity for positive phase

Set up the positive phase range parity of the MBS at location $+\pi$, $+3\pi$ etc. Use the index control on the left to move the display of the array elements. Set the element by enter the value, right click to remove the element.



parity



Strengthen of MBS

Strength of the MBS, "a" parameter of the $\sin(f/2)$ term.



parity for negative phase

Set up the negative phase range parity of the MBS at location -5π , -3π , $-\pi$ etc. Use the index control on the left to move the display of the array elements. Set the element by enter the value, right click to remove the element.



parity



Run

Click to Run the calculation of the diffraction pattern according to the parameters set below. The plots of diffraction pattern, and the phase0 vs flux will be updated during calculation.



Exit

Exit this program, close the app.



hold

Check this to keep the current plot in the next run, such that you can compare plots between different runs.



S-TI-S JJ Simulation.vi

C:\Users\yg\Box\Guang Yue uiuc research box folder\computation\Labview
simulation GUI\S-TI-S JJ Simulation.vi

Last modified on 4/22/2020 at 10:14 AM

Printed on 4/22/2020 at 10:35 AM



Save

Click to save data on the current shown plots. To choose plots, select the interested Tab. The data will be saved as columns of x, y1,y2,y3



Plot tab

Choose the tab to select current plots in the data save process.



Geometry Noise Type

Choose geometry noise type for the current density profile along the y direction. "OFF" assume uniform density of current along the junction.



Plot CPR

Plot CPR according to current setting in the CPR tab.



Plot J vs y

Plot supercurrent vs y position based on the last diffraction pattern calculation.



CPR plot points

Data points needed in the CPR plot.



clearlc

Clear the plot of diffraction pattern and phase0



clear j

Clear the plots of J vs y



clear cpr

Clear the plots of CPR



Plot choice

Choose the data the J vs y plot based on. You can choose the positive or negative diffraction pattern in the last run.



Icp



Icn



Flux

The flux for the J vs y plot



Set Noise

Open up a window to setup noise pattern. Click this button will automatically choose the "Noise ON"



S-TI-S JJ Simulation.vi

C:\Users\yg\Box\Guang Yue uiuc research box folder\computation\Labview
simulation GUI\S-TI-S JJ Simulation.vi

Last modified on 4/22/2020 at 10:14 AM

Printed on 4/22/2020 at 10:35 AM



error out[error out]

This icon will show any errors during the run.



status



code



source



Ic positive

Ic positive in the current calculation



Ic negative

Ic negative in the current calculation



Diffraction pattern plot



Total time s

Total time spent since the start of the calculation.



phaserange in Pi

PhaseRange in the calculation, the CPR will be a periodic function of $[-\text{PhaseRange}/2, \text{PhaseRange}/2]$ range. This value is decided by the choice of CPR type.



Remaining steps

Remaining steps of the diffraction pattern calculation.



Current Flux

Current flux to calculate diffraction pattern.



Positive Phase0

Optimized the phase0 in the positive critical current calculation.



Negative Phase0

Optimized the phase0 in the negative critical current calculation.



Phase0 vs Flux



J vs y



CPR



Actual flux

Actual flux used for the plot, which is reduced to the actual flux of a data point.